# Sensitivity Analysis in SUNDIALS: Current and Coming Attractions

### Radu Şerban

Center for Applied Scientific Computing Lawrence Livermore National Laboratory



Eighth DOE ACTS Collection Workshop August 22, 2007

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks


### **Outline**



- 1 SUNDIALS: overview
- 2 Sensitivity Analysis
  - Overview: what? why? how?
  - Forward sensitivity analysis
  - Adjoint sensitivity analysis
  - Higher-order sensitivities
- 3 Implementation considerations
  - Efficiency issues
  - (Non-)commutativity issues
- 4 CVODES and IDAS
  - Features
  - Usage
  - Examples
- 5 Final remarks

# **Development timeline**





### Solution of large systems in parallel motivated writing (or rewriting) solvers in C

CVODE C rewrite of VODE/VODPK [Cohen, Hindmarsh, 1994]

**PVODE** parallel extension of **CVODE** [Byrne, Hindmarsh, 1998]

KINSOL C rewrite of NKSOL [Taylor, Hindmarsh, 1998]

IDA C rewrite of DASPK [Hindmarsh, Taylor, 1999]

#### Codes organized as a suite (SUNDIALS) in 2002

[Hindmarsh, Brown, Grant, Lee, S., Shumaker, Woodward, 2005]

#### Sensitivity capable solvers in SUNDIALS

**CVODES** [S., Hindmarsh, 2002]

**IDAS** [S., 2007]

SUNDIALS

**Sensitivity Analysis** 

Implementation

CVODES and IDAS

Final remarks

### The SUNDIALS solvers



#### **CVODE - ODE solver**

- Variable-order, variable-step BDF (stiff) or implicit Adams (nonstiff)
- Nonlinear systems solved by Newton or functional iteration
- Linear systems solved by direct (dense or band) or iterative solvers

#### **IDA - DAE solver**

- Variable-order, variable-step BDF
- Nonlinear system solved by Newton iteration
- Linear systems solved by direct or iterative solvers

#### **KINSOL** - nonlinear solver

- Inexact Newton solver (GMRES, BiCG-Stab, or TFQMR iterative linear solvers)
- (Modified) Newton solver (dense or band direct linar solvers)

#### **CVODES**

■ Sensitivity-capable (forward & adjoint) version of **CVODE** 

#### **IDAS**

Sensitivity-capable (forward & adjoint) version of IDA

### Salient features of the SUNDIALS solvers



- Philosophy: Keep codes simple to use
- Written in C
  - Fortran interfaces: FCVODE, FIDA, and FKINSOL
  - Matlab interfaces: **SUNDIALSTB** (**CVODES**, **IDAS**, and **KINSOL**)
- Written in a data structure neutral manner
  - No specific assumptions about data
  - Alternative data representations and operations can be provided
- Modular implementation: vector modules, linear solver modules, preconditioner modules
- Require minimal problem information, but offer user control over most parameters
- Sensitivity Analysis
  - Philosophy: Require minimal changes to enable SA
  - Provide both FSA and ASA support

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

### What is SA?



#### **Definition**

Broadly speaking, *sensitivity analysis* (SA) is the study of how the variation in the output of a model (numerical or otherwise) can be apportioned, qualitatively or quantitatively, to different sources of variation.

Local sensitivity analysis (dynamical systems)

$$F(\dot{y}, y, p) = 0$$
$$g(p) = g(y(p), p)$$

where  $y \in R^n$  and  $g : R^n \times R^{N_p} \to R$ .

Considering the Taylor expansion of g around the nominal value p

$$g(p + \delta p) = g(p) + \frac{dg}{dp} \delta p + (\delta p)^{T} \frac{d^{2}g}{dp^{2}} \delta p + O(\|\delta p\|^{3})$$

we define

- 1<sup>st</sup> order SA problem: find the gradient  $\frac{dg}{dp} = g_y y_p + g_p$
- 2<sup>nd</sup> order SA problem: find the Hessian  $\frac{d^2g}{dp^2} = (I_{N_p} \otimes g_y)y_{pp} + g_{py}^Ty_p + y_p^Tg_{yp} + y_p^Tg_{yy}y_p + g_{pp}$



### Model evaluation

Finding most and least influential parameters

#### Model reduction

Reducing model complexity, while preserving its input-output behavior

#### Data assimilation

Merging observed information into a model in order to improve its accuracy

### Uncertainty quantification

Characterizing (quantitatively) and reducing uncertainty in model predictions

### Dynamically-constrained optimization

Improving model response (better performance, better agreement with observations, etc.)

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# How to perform SA? (1)



### Parameter-dependent ODE system

Model:  $F(\dot{y}, y, p) = 0$ 

Output functional: g(p) = g(y(p), p)

### Finite-difference sensitivity analysis

$$rac{dg}{d
ho_i}(
ho)pprox rac{g(
ho+e_i\delta
ho_i)-g(
ho)}{\delta
ho_i}$$

or

$$rac{dg}{d
ho_i}(
ho)pprox rac{g(
ho+e_i\delta
ho_i)-g(
ho-e_i\delta
ho_i)}{2\delta
ho_i}$$

where  $e_i$  is the *i*-th column of the identity matrix and  $\delta p$  is a vector of perturbations.

# How to perform SA? (2)



### Parameter-dependent ODE system

Model:  $F(\dot{y}, y, p) = 0$ 

Output functional: g(p) = g(y(p), p)

### Forward sensitivity analysis

$$F_{\dot{y}}\dot{s}_i + F_{y}s_i + F_{p_i} = 0$$

and

$$dg/dp = g_{y}s_{i} + g_{p_{i}}$$

Cost  $\sim (1 + N_p) \times cost(sim)$ 

### Adjoint sensitivity analysis

$$-(\lambda^T F_{\dot{y}})' + \lambda^T F_y + h(g) = 0$$

and

$$\langle F_p, \lambda \rangle \to \nabla_p g(p)$$

Cost 
$$\sim (1 + N_g) \times cost(sim)$$

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# **FSA for ODE and DAE systems**



- Parameter dependent system:  $F(\dot{y}, y, p) = 0$ ,  $y(t_0) = y_0(p)$
- Output functional: g(y, p)
- Sensitivity systems:  $(i = 1, 2, ..., N_p)$

$$F_{\dot{y}}\dot{s}_i + F_y s_i + F_{p_i} = 0$$
,  $s_i(t_0) = y_{0p_i}$ 

Gradient of output functional:

$$\frac{dg}{dp}=g_{y}S+g_{p}$$

where  $S = [s_1, s_2, \dots, s_{N_p}]$  is the sensitivity matrix.

- Sensitivity equations depend on p but not on g.
- A linear combination Su of all sensitivity vectors can be computed with  $\sim$  twice the cost of computing y.

# ASA for ODE and DAE systems (1)



Model:  $F(\dot{y}, y, p) = 0$ ,  $y(t_0) = y_0(p)$ 

Output functional:  $G(p) = \int_{t_0}^{t_f} g(y, p) dt$ 

Gradient:  $\frac{dG}{dp} = \int_{t_0}^{t_f} (g_p - \lambda^T F_p) dt - (\lambda^T F_{\dot{y}} y_p)|_{t_0}^{t_f}$ 

Adjoint system:  $(\lambda^T F_{\dot{y}})' - \lambda^T F_y = -g_y$ ,  $\lambda(t_f) = ?$ 

Consistent final conditions [Cao,Li,Petzold,S., 2003]

### index-0 and index-1 DAE

$$F(\dot{y}, y) = 0 \Rightarrow (\lambda^T F_{\dot{y}})' - \lambda^T F_y = -g_y$$

Can use any  $\lambda(t_f)$  such that

$$\left(\lambda^T F_{\dot{y}}\right)_{t=t_f} = 0$$

(in particular  $\lambda(t_f) = 0$ ) and therefore

$$\frac{dG}{dp} = \int_{t_0}^{t_f} \left( g_\rho - \lambda^T F_\rho \right) dt + \left( \lambda^T F_{\dot{y}} \right)_{t=t_0} y_{0\rho}$$

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# ASA for ODE and DAE systems (2)



Model:  $F(\dot{y}, y, p) = 0$ ,  $y(t_0) = y_0(p)$ 

Output functional:  $G(p) = \int_{t_0}^{t_f} g(y, p) dt$ 

Gradient:  $\frac{dG}{dp} = \int_{t_0}^{t_f} (g_p - \lambda^T F_p) dt - (\lambda^T F_{\dot{y}} y_p)|_{t_0}^{t_f}$ 

Adjoint system:  $(\lambda^T F_{\dot{v}})' - \lambda^T F_{\dot{v}} = -g_{\dot{v}}, \quad \lambda(t_f) = ?$ 

Consistent final conditions [Cao,Li,Petzold,S., 2003]

### **Hessenberg index-2 DAE**

$$\dot{y}^d = f^d(y^d, y^a, p) 
0 = f^a(y^d, p) \Rightarrow \dot{\lambda}^d = -A^T \lambda^d - C^T \lambda^a - g_{y^d}^T 
0 = -B^T \lambda^d - g_{y^a}^T$$

Search for final conditions of the form  $\lambda^d(t_f) = (C^T \xi)_{t=t_f}$ 

$$t = t_f \Rightarrow \left\{ egin{array}{l} \lambda^{dT}B = -g_{y^a} \Rightarrow \xi^TCB = -g_{y^a} \Rightarrow \xi^T = -g_{y^a}(CB)^{-1} \ f^a(y^d,p) = 0 
ightarrow Cy_p^d = -f_p^a \Rightarrow \lambda^{dT}y_p^d = -yi^Tf_p^a \end{array} 
ight.$$

# Sensitivity of $g(y(t_f), t_f, p)$ (1)



Use:  $\frac{dg}{dp}(t_f) \equiv \frac{d}{dt_f} \frac{dG}{dp}$ 

Gradient:  $\frac{dg}{dp}(t_f) = (g_p - \lambda^T F_p)_{t=t_f} + \int_{t_0}^{t_f} \mu^T F_p \, dt - (\mu^T F_{\dot{y}} y_p)_{t=t_0} - \frac{d(\lambda^T F_{\dot{y}} y_p)}{dt_f}$ 

Adjoint system:  $(\mu^T F_{\dot{V}})' - \mu^T F_{\dot{V}} = 0$ ,  $\mu(t_f) = ?$ 

Consistent final conditions [Cao,Li,Petzold,S., 2003]

### implicit ODE

$$F(\dot{y}, y) = 0 \Rightarrow (\mu^T F_{\dot{y}})' - \mu^T F_y = 0$$

At  $t = t_f$ 

$$\lambda^T F_{\dot{y}} = 0 \Rightarrow (\lambda^T F_{\dot{y}})' + \mu^T F_{\dot{y}} = 0$$

and therefore

$$\mu^{\mathsf{T}}(t_f) = \left(\mathsf{F}_{\dot{y}}^{-1} \mathsf{g}_{y}\right)_{t=t_f}$$

If 
$$y_0 = y_0(p) \Rightarrow$$

$$\frac{dg}{d\rho}(t_f) = g_{\rho}(t_f) + \mu^{\mathsf{T}}(t_0) A(t_0) y_{0\rho}$$

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# Sensitivity of $g(y(t_f), t_f, p)$ (2)



Use:  $\frac{dg}{dp}(t_f) \equiv \frac{d}{dt_f} \frac{dG}{dp}$ 

Gradient:  $\frac{dg}{dp}(t_f) = (g_p - \lambda^T F_p)_{t=t_f} + \int_{t_0}^{t_f} \mu^T F_p \, dt - (\mu^T F_{\dot{y}} y_p)_{t=t_0} - \frac{d(\lambda^T F_{\dot{y}} y_p)}{dt_f}$ 

Adjoint system:  $(\mu^T F_{\dot{v}})' - \mu^T F_V = 0$ ,  $\mu(t_f) = ?$ 

Consistent final conditions [Cao,Li,Petzold,S., 2003]

### Hessenberg index-1 DAE

$$\dot{y}^d = f^d(y^d, y^a) \\
0 = f^a(y^d, y^a) \Rightarrow \dot{\mu}^d = -A^T \mu^d - C^T \mu^a \\
0 = B^T \mu^d + D^T \mu^a$$

 $A = \partial f^d/\partial y^d$ ,  $B = \partial f^d/\partial y^a$ ,  $C = \partial f^a/\partial y^d$ ,  $D = \partial f^a/\partial y^a$  nonsingular

$$\mu^{dT}(t_f) = \left(g_{y^d} - g_{y^a}D^{-1}C\right)_{t=t_f}$$

If 
$$y_0^d = y_0^d(p) \Rightarrow$$

$$\frac{dg}{dp}(t_f) = g_p(t_f) + \mu^{dT}(t_0)y_{0p}^d$$

# Sensitivity of $g(y(t_f), t_f, p)$ (3)



Use:  $\frac{dg}{dp}(t_f) \equiv \frac{d}{dt_f} \frac{dG}{dp}$ 

Gradient:  $\frac{dg}{dp}(t_f) = (g_p - \lambda^T F_p)_{t=t_f} + \int_{t_0}^{t_f} \mu^T F_p \, dt - (\mu^T F_{\dot{y}} y_p)_{t=t_0} - \frac{d(\lambda^T F_{\dot{y}} y_p)}{dt_f}$ 

Adjoint system:  $(\mu^T F_{\dot{v}})' - \mu^T F_{\dot{y}} = 0$ ,  $\mu(t_f) = ?$ 

Consistent final conditions [Cao,Li,Petzold,S., 2003]

### **Hessenberg index-2 DAE**

$$\dot{y}^d = f^d(y^d, y^a)$$
  $\Rightarrow$   $\dot{\mu}^d = -A^T \mu^d - C^T \mu^a$   $0 = B^T \mu^d$ 

 $A = \partial f^d/\partial y^d$ ,  $B = \partial f^d/\partial y^a$ ,  $C = \partial f^a/\partial y^d$ , CB nonsingular

$$\mu^{dT}(t_f) = \left(g_{y^d} - g_{y^a}(CB)^{-1}\left(CA + \frac{dC}{dt}\right)\right)_{t=t_f} \left(I - B(CB)^{-1}C\right)_{t=t_f}$$

If 
$$y_0^d = y_0^d(p) \Rightarrow$$

$$\frac{dg}{dp}(t_f) = g_p(t_f) + \mu^{dT}(t_0)y_{0p}^d$$

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# **Higher-order sensitivities with FSA**



- Straightforward extension of 1<sup>st</sup> order SA.
- Except when dealing with very few parameters, the computational cost is exorbitant.

### **Example**

ODE 
$$\dot{y} = f(t, y); \quad y(t_0) = y_0(p); \quad y \in \mathbb{R}^n, \ p \in \mathbb{R}^{N_p}$$

Functional g(y(p))

Hessian 
$$\frac{d^2g}{dp^2} = \left(I_{N_p} \otimes g_y\right) y_{pp} + y_p^T g_{yy} y_p$$

where

$$\dot{y}_p = f_y y_p$$
;  $y_p(t_0) = \frac{dy_0}{dp}$ 

$$\dot{y}_{pp} = f_y y_{pp} + \left(I_n \otimes y_p^T\right) f_{yy} y_p; \quad y_{pp}(t_0) = \frac{d^2 y_0}{dp^2}$$

Note that  $dim(y_p) = nN_p$  and  $dim(y_{pp}) = n^2N_p$ .

# **Higher-order sensitivities with ASA**



- Use the same trick as for the "pointwise functional" case: take an additional formal derivatives of the gradient of either *G* or *g*.
- The cost of computing a full Hessian is roughly equivalent to the cost of computing the gradient with FSA. However, Hessian-vector products can be cheaply computed with one additional adjoint solve [Ozyurt and Barton, 2005]

#### **Example**

ODE 
$$\dot{y}=f(t,y)\,; \quad y(t_0)=y_0(p)\,; \quad y\in R^n,\ p\in R^{N_p}$$
Functional  $G(p)=\int_{t_0}^{t_f}g(t,y)\,dt$ 

Hessian-vector product  $\frac{\partial^2 G}{\partial p^2}u=\left[\left(\lambda^T\otimes I_{N_p}\right)y_{pp}u+y_p^T\mu\right]_{t=t_0}$ 
where  $-\dot{\mu}=f_y^T\mu+\left(\lambda^T\otimes I_n\right)f_{yy}s\,; \quad \mu(t_f)=0$ 
 $-\dot{\lambda}=f_y^T\lambda+g_y^T\,; \quad \lambda(t_f)=0$ 
 $\dot{s}=f_ys+f_pu\,; \quad s(t_0)=y_{0p}u$ 

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# Generation of the sensitivity equations



### Forward sensitivity analysis

- Analytical
- Automatic differentation (ADIC, ADOLC)
- Directional derivative approximations

$$\begin{cases} f_{y}s_{i} \approx \frac{f(t,y+\sigma_{y}s_{i},p)-f(t,y-\sigma_{y}s_{i},p)}{2\sigma_{y}} \\ f_{p_{i}} \approx \frac{f(t,y,p+\sigma_{i}e_{i}p)-f(t,y,p-\sigma_{i}e_{i})}{2\sigma_{i}} \end{cases} \qquad \begin{cases} \sigma_{i} = |\bar{p}_{i}|\sqrt{\max(rtol,\epsilon)} \\ \sigma_{y} = \frac{1}{\max(1/\sigma_{i},\|s_{i}\|_{WRMS}/|\bar{p}_{i}|)} \end{cases}$$

or

$$f_{y}s_{i} + f_{p_{i}} \approx \frac{f(t, y + \sigma s_{i}, p + \sigma e_{i}p) - f(t, y - \sigma s_{i}, p - \sigma e_{i})}{2\sigma}$$

where  $\sigma = \min(\sigma_i, \sigma_y)$ 

### Adjoint sensitivity analysis

- Analytical
- Reverse automatic differentiation (ADOLC)
- No finite-difference option (cost  $\sim$  cost<sub>FSA</sub>)

SUNDIALS Sensitivity Analysis

### Implementation CVODES and IDAS ○●○○ ○○○○○

### Final remarks

# **FSA** with implicit solvers



FSA effectively implies solving an extended system of dimension  $N \times N_p \Rightarrow$  efficient implementation of an implicit integrator must take advantage of the structure of the sensitivity equations and the fact that they are linearizations of the original DE.

#### Solutions (for implicit ODE/DAE integrators)

- Staggered Direct [Caracotsios and Stewart, 1985]: iterate to convergence the nonlinear state system and then solve the linear sensitivity systems requires formation and storage of J; errors in J → errors in s
- Simultaneous Corrector [Maly and Petzold, 1997]: solve simultaneously a nonlinear system for both states and sensitivity variables requires formation of sensitivity r.h.s. at every iteration
- Staggered Corrector [Feehery, Tolsma, and Barton, 1997]: iterate to convergence the nonlinear state system and then use a Newton method to solve for the sensitivity variables with iterative linear solvers → effectively Staggered Direct

SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

### **ASA for nonlinear problems**



For nonlinear problems, the forward states are needed in the backward integration phase. Moreover, when using an adaptive integrator, the number of integration steps is not known apriori and the forward and backward DE are evaluated at different times.  $\Rightarrow$  need predictable and compact storage of state variables for the solution of the adjoint system and an efficient interpolation scheme.

#### Solution: checkpointing


Represents a compromise between efficiency and memory requirements:

- Simulations are reproducible from each checkpoint
- Force Jacobian evaluation at checkpoints to avoid storing it
- Store solution (and possibly first derivative) at all intermediate steps between two consecutive checkpoints
- Interpolation options: cubic Hermite, variable-order polynomial

### CASC

#### **Implementation**

- 1 integrate forward step by step
- 2 dump checkpoint data after a given number of steps
- 3 continue until  $t_f$ .
- 4 evaluate final conditions for adjoint problem
- 5 store interpolation data on second forward pass
- 6 propagate adjoint variables backward in time
- 7 1 forward + 1 backward < total cost < 2 forward + 1 backward



**SUNDIALS** 

**Sensitivity Analysis** 

Implementation 00000

**CVODES and IDAS** 

Final remarks

# Discrete vs. continuous sensitivity



#### Discretization of the adjoint vs. adjoint of the discretization?

- Discrete adjoint of a RK method of order p is an order p discretization of the adjoint equations [Hager, 2000].
- BDF adjoints with variable step are not consistent with the continuous adjoint equation [Sandu, 2003].

#### Time-dependent PDE solved with MOL: additional issues

- DA: discretization of the adjoint PDE
  - no general derivation method (hard for systems of PDEs).
  - some objective functionals may be inadmissible [Arian and Salas, 1997; Giles and Pierce, 1997].
- AD: adjoint of the semi-discretization to ODE/DAE
  - do not require explicit BC for adjoint variables.
  - any cost functional is admissible.
  - may be inconsistent with the adjoint PDE (e.g. when using nonlinear discretization schemes).
  - may not be consistent with any PDE close to boundaries [Li and Petzold, 2004].

### Salient features of the SUNDIALS SA solvers



- Solution of nonlinear systems for FSA
  - simultaneous corrector
  - staggered corrector
  - modified staggered corrector (CVODES only)
- Two-pass checkpointing for ASA
- Two different interpolation modules for ASA:
  - piece-wise cubic Hermite
  - variable-order polynomial
- Support for integration of pure quadrature equations (for the evaluation of integrals in ASA)
- Support for simultaneous integration of multiple adjoint problems and of adjoint problems depending on forward sensitivities (for 2nd order ASA)
- Calculation of consistent initial conditions for state, sensitivity, and adjoint variables (IDAS only)
- Generation of the FSA sensitivity systems through directional derivatives

SUNDIALS

**Sensitivity Analysis** 

Implementation

CVODES and IDAS

Final remarks

### **IVP** integration with CVODES



```
Main function

/* Set tolerances, initial time, etc. */
y = N_VNew_Serial(N);
/* Load I.C. into y */
mem = CVodeCreate(CV_BDF, CV_NEWTON);
flag = CVodeSetUserData(mem, my_data);
/* Set other optional inputs */
flag = CVodeInit(mem, rhs, t0, y);
flag = CVodeStolerances(mem, rtol, atol);
flag = CVDense(mem, N);
for(i=1; i<= NOUT; i++) {
   flag = CVode(mem, tout, y, &t, CV_NORMAL);
   /* Process solution y */
}
N_VDestroy(y);
CVodeFree(&mem);</pre>
```

### **User-supplied functions**

```
required
int rhs(realtype t, N_Vector y, N_Vector f, void *data);
optional
Jacobian information, preconditioner, rootfinding, quadrature, etc.
```

### **FSA** with cvodes



#### Main function (instrumented for FSA)

```
y = N_VNew_Serial(N);
mem = CVodeCreate(CV_BDF, CV_NEWTON);
flag = CVodeSet***(mem,...);
flag = CVodeInit(mem, rhs, t0, y);
flag = CVodeSStolerances(mem, rtol, atol);
flag = CVDense(mem, N);
yS = N_VCloneVectorArray(Ns, N);
flag = CVodeSensInit(mem, Ns, CV_STAGGERED, srhs, yS);
flag = CVodeSensEEtolerances(mem);
flag = CVodeSetSens***(mem,...);
for(i=1; i<= NOUT; i++) {
  flag = CVode(mem, tout, y, &t, CV_NORMAL);
  flag = CVodeGetSens(mem, &t, yS);
N_VDestroy(y);
N_VDestroyVectorArray(Ns, yS);
CVodeFree(&mem);
```

#### **User-supplied functions**

#### recommended

SUNDIALS

**Sensitivity Analysis** 

**Implementation** 

CVODES and IDAS

Final remarks

### **ASA** with cvodes



### Main function (instrumented for ASA)

```
y = N_VNew_Serial(N);
mem = CVodeCreate(CV_BDF, CV_NEWTON);
flag = CVodeSet***(mem, my_data);
flag = CVodeInit(mem, rhs, t0, y);
flag = CVodeSStolerances(mem, rtol, atol);
flag = CVDense(mem, N);
flag = CVodeAdjInit(mem, nsteps, CV_POLYNOMIAL);
for(i=1; i<= NOUT; i++) {
   /*flag = CVode(mem, tout, y, &t, CV_NORMAL);
  flag = CVodeF(mem, tout, y, &t, CV_NORMAL, &nckeck);
yB = N_VNew_Serial(NB);
flag = CVodeCreateB(mem, CV_BDF, CV_NEWTON, &idxB);
flag = CVodeInitB(mem, idxB, rhsB, tf, yB);
flag = CVodeSet***B(mem, idxB,...);
flag = CVodeB(mem, t0, CV_NORMAL);
flag = CVodeGetB(mem, idxB, &t, yB);
N_VDestroy(y);
N_VDestroy(yB);
CVodeFree(&mem);
```

#### **User-supplied functions**

#### required

int rhsB(realtype t, N\_Vector y, N\_Vector yB, N\_Vector fB, void \*data);
optional

Jacobian information, preconditioner, quadrature, etc.

position constraints velocity constraints


# FSA example: slider-crank




**Dynamics** stabilized index-2 DAE (GGL formulation)

$$\begin{cases} \dot{q} = v - \Phi_q^T(q)\mu \\ M(q)\dot{v} = Q(q, v, k, c) - \Phi_q^T(q)\lambda \\ \Phi(q) = 0 \\ \Phi_q(q)v = 0 \end{cases}$$

I.C. 
$$q(0) = q_0$$
,  $v(0) = v_0$ 





SUNDIALS

Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

# **ASA** example: brusselator



**Dynamics** 

Two-species 2D time-dependent PDE

$$\begin{cases} u_t = \epsilon \Delta u + u^2 v - (B+1)u + A \\ v_t = \epsilon \Delta v - u^2 v + Bu \end{cases}$$

in 
$$\Omega = [0, L]^2$$

B.C. 
$$(\partial u/\partial n)|_{\partial\Omega} = (\partial v/\partial n)|_{\partial\Omega} = 0$$

I.C. 
$$u(x, y, t_0) = u_0(x, y) \equiv 1.0 - 0.5 \cos(\pi y/L)$$
  
 $v(x, y, t_0) = v_0(x, y) \equiv 3.5 - 2.5 \cos(\pi x/L)$ 

**Output** 

$$g(t) = (1/|\Omega|) \int_{\Omega} u(x, y, t) d\Omega$$

**Adjoint PDE** 

$$\begin{cases} \lambda_t = -\epsilon \Delta u - (2uv - B - 1)\lambda + (2uv - B)\mu \\ \mu_t = -\epsilon \Delta v - u^2 \lambda - u^2 \mu \end{cases}$$

B.C. 
$$(\partial \lambda/\partial n)|_{\partial\Omega} = (\partial \mu/\partial n)|_{\partial\Omega} = 0$$

I.C. 
$$\lambda(x, y, t_f) = 1.0$$
  
 $\mu(x, y, t_f) = 0.0$ 

Sensitivity  $\delta t$ 

$$\delta u_0, \delta v_0 \Rightarrow \delta g(t_f)$$


$$g(t_f) = (1/|\Omega|) \int_{\Omega} \left[ \lambda(0, x, y) \delta u_0(x, y) + \mu(0, x, y) \delta v_0(x, y) \right] d\Omega$$

# **ASA example: brusselator**

**Sensitivity Analysis** 




Initial conditions  $u(t_0, x, y) \equiv u0(x, y)$ 




Final solution  $u(t_f, x, y)$ 


000000



Adjoint variables  $dg(t_f)/du_0 \equiv \lambda(t_0, x, y)$ 



Weak parallel scaling (jacquard.nersc.gov)



**SUNDIALS** 

**Sensitivity Analysis** 

Implementation

**CVODES and IDAS** 

**Final remarks** •00

# Coming attractions in SUNDIALS



#### SUNDIALS

- IDAS- DAE solver with SA capabilities
- **CPODES** Coordinate projection solver for ODE with invariants
- New linear solver modules
  - Direct dense and band Blas+Lapack linear solvers
  - Support for sparse direct linear solvers

#### **FSA**


Support for FSA of pure quadrature variables

### ASA

- Support for simultaneous integration of multiple backward problems
- Support for simultaneous FSA-ASA (for 2nd order SA using forward over adjoint)

# www.llnl.gov/casc/sundials





#### The SUNDIALS suite

- Open source, BSD license
- Extended documentation
- User support

SUNDIALS 000 Sensitivity Analysis

Implementation

CVODES and IDAS

Final remarks

○○●

# Sensitivity Analysis is...



- useful in several different areas (e.g. dynamically-constrained optimmization, UQ).
- enabling for various types of analysis (ROM evaluation, global error analysis, solution of certain classes of problems).
- only a few function calls away and general-purpose SA solvers are available.
- worthy and the effort required to add sensitivity capabilities to a simulation tool is well invested.

### **UCRL-PRES-213978**

This document was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

This work was performed under the auspices of the U.S. Department of Energy by the University of California, Lawrence Livermore National Laboratory under Contract No. W-7405-Eng-48.